

Minimum requirements to run Python Script that uses KYFGLib.dll Library:

1. Python 3.6 64-bit should be installed in system
Note: If Python 32-bit will be installed there might be an error to load dll
2. Make sure Vision Point is installed in the system
3. Please copy the file KYFGLib.py from directory:
C:\Program Files\KAYA Instruments\Common\bin
into the directory:
C:\Users\User-Name\AppData\Local\Programs\Python\Python36\Lib
(that is the default path, yours might be different)
4. Python script that uses KYFGLib.dll should import the library KYFGLib.py (see KYFGLib_API_Sample.py)
5. Following command will run the sample:
python3 KYFGLib_API_Sample.py